Sommario

Comandi per OpenEnergyMonitor 3
Inviare un dato a EmonCMS 3
Configurazione EmonHub 3

Comandi per OpenEnergyMonitor

Inviare un dato a EmonCMS

```
http://www.emon62.altervista.org/emoncms/input/post.json?node=20&csv=0,0,230&apikey
=xxxxxxxxxxxxx
```

Configurazione EmonHub

```
# SPECIMEN emonHub configuration file
# Note that when installed from apt, a new config file is written
# by the debian/postinst script, so changing this file will do
# nothing in and of itself.

# Each Interfacer and each Reporter has
# - a [[name]]: a unique string
# - a type: the name of the class it instantiates
# - a set of init_settings (depends on the type)
# - a set of runtimesettings (depends on the type)
# Both init_settings and runtimesettings sections must be defined,
# even if empty. Init settings are used at initialization,
# and runtime settings are refreshed on a regular basis.

# All lines beginning with a '#' are comments and can be safely removed.

########################################################################
######################    emonHub  settings    ######################
########################################################################
[hub]

# loglevel must be one of DEBUG, INFO, WARNING, ERROR, and CRITICAL
# see here : http://docs.python.org/2/library/logging.html
loglevel = WARNING

########################################################################
######################        Reporters        ######################
########################################################################
[reporters]

# This reporter sends data to emonCMS
[[emonCMS]]
    Type = EmonHubEmoncmsReporter
    [[[init_settings]]]
    [[[runtimesettings]]]
    # url = http://emoncms.org
        # apikey = 6a07b7a3ce8de000fee769cbc829f09f
    url = http://emon62.altervista.org
        apikey = 6b3c81f5b732f6fe4c899a7e2ea32620

########################################################################
######################       Interfacers       ######################
```

```
##############################################################################
[interfacers]

# This interfacer manages the RFM2Pi module
[[RFM2Pi]]
    Type = EmonHubJeeInterfacer
    [[[init_settings]]]
        com_port = /dev/ttyAMA0
    [[[runtimesettings]]]
        group = 210
        frequency = 433
        baseid = 10

##############################################################################
########################          Nodes          ########################
##############################################################################
[nodes]

# List of nodes by node ID
# 'datacode' is default for node and 'datacodes' are per value data codes.
# if both are present 'datacode' is ignored in favour of 'datacodes'
[[99]]
    datacode = h
    datacodes = l, h, h, h,
```

Fonte:
Wiki - Progetti

Autore:
Walter62

Ultimo aggiornamento: **2023/01/01 17:03**